

USB3.0 Dram Disk Recovery Tool User Manual



Aug. 06, 2013

Ver. 0.1.2

Introduction

A. Notice

B. Open the File

C. Use the Recovery Tool


D. Use the AP Tool

A. Notice


1. The Recovery Tool is only used when USB3.0 Dram Disk is **malfunction** or **update the AP**.
2. Please **do not** use this tool when USB3.0 Dram Disk is functionally well.
3. All Data would be **ERASED**! Please Noted.

B. Open the file

- (1). Go to download folder.
- (2). Open file, Dram_Disk_Factory_Restore.exe



- In Windows 7 / Vista, you would allow UAC to execute this application.
- (3). UAC protect, please click [Yes].




- Please **insert** your USB3.0 Dram Disk **FIRST!**
(4). Click [Yes] to execute Recovery Tool.



C. Run the Recovery Tool

(5). Select the Drive Letter.

(6). Click [Start].




Press start

Select the Drive

Please do not close the black one. It will close by itself.

- Please read carefully, the drive data would be erased.
(7). Click [Yes] and continue.



The Process bar Status

(8). If Success, then click [OK] and go to next step.
If fail or else situation, please check page 15 FAQ.



- Please re-plugin USB drive. The Screen would be like below.
(9). Wait the [AI Recovery] can detect USB drive, and click [X] to close application.




D. Run the AP Tool

- Please unplug USB drive. The Screen would be like below.




(10). The AP would detect the Target Drive and auto start.


(10)




- (11). If unplug, it would show below information, and require re-plug in the Target USB Drive.
- It would take 1~2 minutes, please wait.



(12). If re-plugin, the program would start to format the Target Drive.



(13). When the Format complete, it would show [PASS!!], just click the [OK] button. The Target Drive had completed update.



FAQ

- If failure, please **reboot** your computer and try standard step again, or just close the [AI Recovery] program, go to next step.
- If any question about this manual, please contact support@supertalent.com

SUPER ★ TALENT®
THE BEST MEMORY